# \_示例代码\_单电机

2019年4月12日 20:07

```
Im1 = LargeMotor(OUTPUT_A)
Im2 = LargeMotor(OUTPUT_B)
mm = MediumMotor(OUTPUT_D)
```

#### 查看连接端口

```
debug_print('address: ', mm.address)
address: ev3-ports:outD
```

### 查看可执行指令

debug print('commands: ', mm.commands)

```
commands: ['run-forever', 'run-to-abs-pos',
'run-to-rel-pos', 'run-timed', 'run-direct',
'stop', 'reset']
```

### 查看电机每1转的计数

```
debug_print('count per rotation for LargeMotor: ', lm1.count_per_rot)
debug_print('count per rotation for MediumMotor: ',
mm.count per rot)
```

count per rotation for LargeMotor: 360

count per rotation for MediumMotor: 360

# 查看该电机驱动器的名称

```
debug_print('driver name: ', mm.driver_name)
river name: lego-ev3-m-motor
```

### 查看占空比,

```
debug_print('current duty circle: ', mm.duty_cycle)
```

current duty circle: 0

### 写入设置占空比设定值, 返回当前值

debug\_print('set duty circle: ', mm.duty\_cycle\_sp)

set duty circle: 0

### 设置占空比设定值

mm.duty\_cycle\_sp = -80

debug\_print('current duty circle setted: ', mm.duty\_cycle\_sp)

current duty circle setted: -80

### 电机的极性

如果设置为'normal', +值正转

如果设置为'inversed', +值反转

debug\_print('polarity for LargeMotor: ', lm1.polarity)

debug\_print('polarity for MediumMotor: ', mm.polarity)

polarity for LargeMotor: normal

polarity for MediumMotor: normal

### 查看电机在旋转中的位置(可看作在一条数轴上左右移动)

顺时针旋转时数值增加, 逆时针旋转时数值减小

debug\_print('position: ', mm.position)

position: 0

### 查看位置PID的比例常数

debug\_print('位置pid的比例常数: ', mm.position\_p) \u4f4d\u7f6epid\u7684\u6bd4\u4f8b\u5e38\u6570\uff1a 160000

# 查看位置PID的积分常数

debug\_print('位置pid的积分常数:', mm.position\_i) \u4f4d\u7f6epid\u7684\u79ef\u5206\u5e38\u6570\uff1a 0

# 查看位置PID的导数常数

debug\_print('位置pid的导数常数: ', mm.position\_d) \u4f4d\u7f6epid\u7684\u5bfc\u6570\u5e38\u6570: 0

查看为以位置为基础的运行模式设置的目标位置,可转换为角度或

#### 旋转数

debug\_print('不知道是啥: ', mm.position\_sp) \u4e0d\u77e5\u9053\u662f\u5565: 0

#### 查看理论上的最大速度

debug\_print('max speed for LargeMotor', mm.max\_speed)
debug\_print('max speed for MediumMotor', lm1.max\_speed)
max speed for LargeMotor 1560
max speed for MediumMotor 1050

读取当前每秒tacho计数,负值代表反方向旋转 debug\_print('current motor speed in tacho count: ', mm.speed) current motor speed in tacho count: 0

### 读取当前提升设定值

debug\_print('current ramp up speed: ', mm.ramp\_up\_sp)
current ramp up speed: 0

### 读取当前减小设定值

debug\_print('current ramp down speed: ', mm.ramp\_down\_sp)
current ramp down speed: 0

# 查看速度调节pid的比例常数

debug\_print('速度调节pid的比例常数', mm.speed\_p)
\u901f\u5ea6\u8c03\u8282pid\u7684\u6bd4\u4f8b\u5e38
\u6570 1000

# 查看速度调节pid的积分常数

debug\_print('速度调节pid的积分常数', mm.speed\_i)
\u901f\u5ea6\u8c03\u8282pid\u7684\u79ef\u5206\u5ea8

\u6570 60

### 查看速度调节pid的导数常数

debug\_print('速度调节pid的导数常数', mm.speed\_d) \u901f\u5ea6\u8c03\u8282pid\u7684\u5bfc\u6570\u5e38 \u6570 0

查看可允许的状态,如'running'、'ramping'、'holding' debug\_print('a list of state flags for MediumMotor', mm.state) debug\_print('a list of state flags for LargeMotor', lm1.state) a list of state flags for MediumMotor [] a list of state flags for LargeMotor []

#### 查看停止状态下的行为表

debug\_print('all stop actions for MediumMotor', mm.stop\_actions) debug\_print('all stop actions for LargeMotor', lm1.stop\_actions) all stop actions for MediumMotor ['coast', 'brake', 'hold'] all stop actions for LargeMotor ['coast', 'brake', 'hold']

### 设置停止状态下的行为

mm.stop\_action = 'hold'

debug\_print('current stop action: ', mm.stop\_action)

current stop action: hold

### 查看 'run-timed'状态下需要持续的时间

debug\_print('the amount of time the motor will run in ''runtimed mode' , mm.time\_sp)

the amount of time the motor will run in run-timed mode 0

根据'duty\_cycle\_sp'设置的占空比运转,与其他command不同,对'duty\_cycle\_sp'的修改即时执行

```
杳看电机是否供电
if mm.is running is None:
debug_print('no')
else:
debug print(mm.is running)
False
查看电机在达到稳定值前是否增加或减小
if mm.is ramping is None:
debug print('no')
else:
debug print(mm.is ramping)
False
判断电机是停止转变还是保持固定值
if mm.is holding is None:
debug print('no')
else:
debug_print(mm.is_holding)
False
查看电机是否过载
if mm.is overloaded is None:
debug_print('no')
else:
debug print(mm.is overloaded)
False
查看电机是否故障
```

```
if mm.is stalled is None:
debug print('no')
else:
debug print(mm.is stalled)
False
阻塞直到电机状态变为
`stalled`或`holding`
(run timed等函数根据speed等sp全局变量运行,因此需要在使用前修改对应值)
sv.speed sp = int(SpeedDPS(360).to native units(sv))
sv.time sp = int(10 * 1000)
sv.run timed()
sv.wait_until_not_moving() # 这里的not_moveing是指run_timed
执行完毕
阻塞直到状态变为 s
sv.speed sp = int(SpeedDPS(360).to native units(sv))
sv.time sp = int(10 * 1000)
sv.run timed()
sv.wait until('stalled')
阻塞直到 s 不再为当前状态(self.state)
debug print('wait while')
sv.speed sp = int(SpeedDPS(360).to native units(sv))
sv.time sp = int(10 * 1000)
sv.run timed()
sv.wait while('running')
控制电机根据旋转数和速度运转
```

lm1.on\_for\_rotations(SpeedRPS(-1), 5)

控制电机根据角度和速度运转

lm2.on\_for\_degrees(SpeedPercent(80), -720)

控制电机根据位置和速度运转

lm1.on\_to\_position(SpeedDPS(180), -80)

控制电机根据速度、持续时间旋转

lm2.on for seconds(SpeedPercent(-80), 3)

Im2.on\_for\_seconds(SpeedPercent(80), 3) # 上一个执行完再执行下一个,不考虑time.sleep

控制电机按照速度持续运转

Im1.on(SpeedPercent(50))

控制电机停止运转

Im1.off()

返回当前旋转圈数

debug\_print('current rotations: ', lm1.rotations)

current rotations: 2.669444444444443

返回旋转角度

debug\_print('current degrees: ', Im1.degrees)

current degrees: 964.999999999999